

STEP-BY-STEP INSTRUCTIONS I

INDESIGN: PRINT SETTINGS FOR PANTONE PLUS COLOURS

InDesign print settings for your Epson photo printer

Before you start, ensure you are using the best and most up-to-date version of everything (firmware, printer drivers etc.) and calibrate your printer. Create your file with PANTONE PLUS colours.

Please follow the steps below and select the highlighted print settings for the best possible print results (You can leave all other settings unchanged or select individual ones as required):

Color Settings

Unsyncronized: Your Creative Suite applications are not synchronized for consistent color. To synchronize, select Suite Color Settings in Bridge.

Settings: Custom
 Advanced Mode

1 Working Spaces
 RGB: Adobe RGB (1998)
 CMYK: ISO Coated v2 (ECI)

Color Management Policies
 RGB: Off
 CMYK: Off

Profile Mismatches: Ask When Opening
 Ask When Pasting

Missing Profiles: Ask When Opening

2 Conversion Options
 Engine: Adobe (ACE)
 Intent: Absolute Colorimetric
 Use Black Point Compensation

Description:
Position the pointer over a heading to view a description.

New Color Swatch

Swatch Name: PANTONE 100 C
 Name with Color Value

3 Color Type: Spot
 Color Mode: RGB

Red: 241
 Green: 227
 Blue: 101

Print

Print Preset: [Custom]
4 Printer: Your Epson photo printer
 PPD: []

Color Management
 Print
 Document (Profile: Adobe RGB (1998))
 Proof (Profile: ISO Coated v2 (ECI))

Options
5 Color Handling: Let InDesign Determine Colours
 Printer Profile: Printer + Premium Semimatte Photo Paper (260)
 Output Color: Composite RGB
 Preserve RGB Numbers
 Simulate Paper Color

Description:
Position the pointer over a heading to view a description.

Save Preset... Page Setup... Print Cancel

Current Settings

Main
 Media Type: Premium Semimatte Photo Paper (260)
6 Print Quality Level: LEVEL 5
 Print Quality: SuperPhoto - 2880x1440dpi
 High Speed: Off
 Color: Off
 Source: Roll Paper
 Auto Cut: Normal Cut
 Auto Rotate: Off
 Page Layout: Portrait
 Orientation: Portrait
 Rotate 180°: Off
 Mirror Image: Off
 Copies: 1
 Size: Pantone
 Job Settings: Off
 Color Correction: Off (No Color Adjustment)
 Always show Current Settings.

Properties of your Epson photo printer

Select Setting: Current Settings
 Media Settings
6 Media Type: Premium Semimatte Photo Paper (260)
 Color: Color
7 Print Quality: Quality Options
 Mode: Automatic Custom
8 Off (No Color Adjustment)
 Paper Settings
 Source: Roll Paper
 Size: Pantone
 Borderless
 Ink Levels
 GR LLK Y LC VLM OR MK VM LK C PK
 Version 6.73

Reset Defaults(Y) OK Cancel Help





Any questions? If so, please contact your dealer for further information.

STEP-BY-STEP INSTRUCTIONS I

INDESIGN: PRINT SETTINGS FOR PANTONE PLUS COLOURS

InDesign print settings for your Canon photo printer

Before you start, ensure you are using the best and most up-to-date version of everything (firmware, printer drivers etc.) and, if possible, calibrate your printer to PANTONE® VIBRANT by Felix Schoeller. Create your file with PANTONE PLUS colours. Please follow the steps below and select the highlighted print settings for the best possible print results (You can leave all other settings unchanged or select individual ones as required):



Any questions? If so, please contact your dealer for further information.